

Software Installation Guide

IRIS Radar
IRIS and RDA



VAISALA

PUBLISHED BY

Vaisala Oyj

Vanha Nurmijärventie 21, FI-01670 Vantaa, Finland

P.O. Box 26, FI-00421 Helsinki, Finland

+358 9 8949 1

vaisala.com

docs.vaisala.com

© Vaisala 2025

No part of this document may be reproduced, published, or publicly displayed in any form or by any means, electronic or mechanical (including photocopying), nor may its contents be modified, translated, adapted, sold, or disclosed to a third party without prior written permission of the copyright holder. Translated document and translated portions of the document are based on the original English version. Parts of the translation may have been created using machine-assisted translation. In ambiguous cases, the English version is applicable, not the translation.

The contents of this document are subject to change without prior notice.

Local rules and regulations applicable to the products and services may vary, and they shall take precedence over the information contained in this document. Vaisala makes no representations on this document's compliance with the local rules and regulations applicable at any given time, and hereby disclaims any and all responsibilities related thereto. You are instructed to confirm the applicability of the local rules and regulations and their effect on the intended use of the products and services.

This document does not create any legally binding obligations for Vaisala towards customers or end users. All legally binding obligations are set forth exclusively in the applicable contract or in the relevant set of General Conditions of Vaisala (vaisala.com/policies).

This product contains software developed by Vaisala or third parties. Use of the software is governed by license terms and conditions included in the applicable contract or, in the absence of separate license terms and conditions, by the General License Conditions of Vaisala Group.

This product may contain open-source software (OSS) components. In the event this product contains OSS components, then such OSS is governed by the terms and conditions of the applicable OSS licenses, and you are bound by the terms and conditions of such licenses in connection with your use and distribution of the OSS in this product. Applicable OSS licenses are included in the product itself or provided to you on any other applicable media, depending on each individual product and the product items delivered to you.

Table of contents

1.	About this document	7
1.1	Version information.....	7
1.2	Related documents.....	7
1.3	Documentation conventions.....	8
1.4	Trademarks.....	8
2.	File system hierarchy tree	9
3.	Preparing for installation	11
3.1	Hardware recommendations.....	11
3.2	Installation image options.....	11
4.	Upgrading AlmaLinux 8.7 to AlmaLinux 9	13
5.	Installing IRIS/RDA and AlmaLinux with Kickstart	16
5.1	Creating installation media.....	16
5.1.1	Creating USB installation media on Windows.....	16
5.1.2	Creating USB installation media on Linux (AlmaLinux).....	17
5.2	Running the installation with Kickstart.....	18
5.3	First login and password change.....	20
5.4	Enabling login as root for using IRIS Focus.....	21
5.5	Verifying that the services are running.....	21
5.6	Configuring IRIS license setups.....	23
6.	Installing IRIS/RDA software (standalone)	26
6.1	IRIS/RDA installation overview.....	26
6.2	Logging in as root.....	26
6.3	Mounting the installation media and verifying the mount point.....	26
6.4	Opening a terminal window.....	27
6.5	Running the installation script.....	28
6.6	First login and password change.....	30
6.7	Verifying that the services are running.....	30
7.	Upgrading IRIS and RDA software	31
7.1	IRIS RDA upgrade overview.....	31
7.2	Preparing for the upgrade.....	31
7.3	Getting upgrade software.....	32
7.3.1	Downloading upgrade files.....	32
7.4	Running the upgrade script.....	33
7.5	Running Setup after upgrade.....	34
7.5.1	Invoking Setup and built-in error checking.....	34
7.6	Checking the kernel module status.....	37
8.	Configuration	38
8.1	Configuring RDA software.....	38
8.2	Configuring firewall.....	39
8.2.1	Configuring the firewall.....	39
8.2.2	Configuring the IFDR10 interface.....	39
8.2.3	Radar cabinet interface.....	40
8.2.4	Remote IRIS menu interface.....	41
8.3	Configuring SSH.....	41
9.	Installing IO-62 firmware	43

- 10. Installing RVP10 (RDA) firmware..... 45**
- 11. Login, logout, and shutdown..... 49**
 - 11.1 Powering up..... 49
 - 11.2 Local and remote login..... 49
 - 11.3 Default usernames and passwords..... 49
 - 11.4 Running commands with root privileges..... 49
 - 11.5 Local login as operator after powerup..... 50
 - 11.6 Powering off..... 50
- 12. Troubleshooting..... 51**
 - 12.1 Correcting file ownership and protection..... 51
 - 12.2 Authorizing remote X-Windows on your node..... 51
 - 12.3 Making Quick Look Windows (QLW) appear..... 52
 - 12.4 Replacing failed OS RAID disks..... 53
- Appendix A: Installing AlmaLinux..... 55**
 - A.1 Overview to installing AlmaLinux 55
 - A.2 Creating installation media..... 55
 - A.2.1 Creating USB installation media on Windows..... 55
 - A.2.2 Creating USB installation media on Linux (AlmaLinux)..... 57
 - A.3 Installing AlmaLinux automatically..... 57
 - A.4 Installing AlmaLinux manually (interactive)..... 63
 - A.4.1 Booting the system for manual installation..... 63
 - A.4.2 Configuring the system and network..... 65
 - A.4.3 Partitioning the destination disk..... 69
 - A.4.4 Starting the installation..... 76
 - A.4.5 Disabling monitor negotiation..... 76
 - A.4.6 Configuring time sync with chronyd..... 77
 - A.4.7 Rebooting the system..... 78
 - A.4.8 Logging in with your user account..... 78
- Appendix B: IRIS Diagnostic Utilities..... 79**
 - B.1 ps_iris command..... 79
 - B.2 show_iris command..... 80
 - B.3 sigmet_env Command..... 82
- Appendix C: Alternative Configurations..... 84**
 - C.1 Defining the operator list in the startup file..... 84
- Warranty..... 85**
- Technical support..... 85**
- Recycling..... 85**

List of tables

Table 1	Related documents (English).....	7
Table 2	RDA configuration tools.....	38
Table 3	Recommended disk partitioning.....	69

1. About this document

1.1 Version information

This document provides information for system managers about installing and upgrading IRIS and RDA software.

Familiarity with operating system concepts is required.

Document code	Date	Description
M212924EN-C	February 2025	Updated for IRIS RDA 10.2.0 Updates include: <ul style="list-style-type: none"> • Recommendations for server computer were added. See Hardware recommendations (page 11). • Corrections to commands in Remote IRIS menu interface (page 41) • Notification conventions updated according to the ANSI Z535.6 standard. See Documentation conventions (page 8).
M212924EN-B	August 2024	Updated for IRIS RDA 10.1.0 Updates include: <ul style="list-style-type: none"> • Operating system changed to AlmaLinux 9. OS installation instructions updated. • Upgrade instructions updated. • Default passwords updated. • Information on firewall configuration added. • Appendix <i>structmap</i> command moved to <i>IRIS Programming Guide (M212927EN)</i>. • Appendix <i>Installing IRIS 3DView</i> removed (no longer supported).
M212924EN-A	May 2023	First version of this document. This document describes IRIS v. 10.0.0, which supports RVP10 Digital Receiver and Signal Processor. The predecessor of this document is M211315EN, which describes IRIS versions that support RVP900 and earlier versions of RVP.

1.2 Related documents

Table 1 Related documents (English)

Document code	Name
DOC236879	<i>IRIS RDA Release Notes</i>
M212924EN	<i>IRIS and RDA Software Installation Guide</i>
M212925EN	<i>IRIS and RDA Utilities Guide</i>
M212926EN	<i>IRIS Radar User Guide</i>

Document code	Name
M212927EN	<i>IRIS Programming Guide</i>
M212928EN	<i>IRIS Product and Display Guide</i>
M212923EN	<i>Radar Control Processor RCP8 User Guide</i>
M212604EN	<i>RVPI0 Digital Receiver and Signal Processor User Guide</i>

1.3 Documentation conventions



NOTICE! Notice alerts you to a situation that, if not avoided, could result in the product to be damaged or important data to be lost.



Highlights important information on using the product.



Gives tips for using the product more efficiently.

1.4 Trademarks

IRIS™ is a trademark of Vaisala Oyj.

AlmaLinux™ is a trademark of AlmaLinux OS Foundation.

Linux® is a registered trademark of Linus Torvalds.

All other product or company names that may be mentioned in this publication are trade names, trademarks, or registered trademarks of their respective owners.

2. File system hierarchy tree

```

|— etc
|   |— vaisala
|   |   |— irisrda
|   |   |   |— images
|   |   |   |— init
|   |   |   |— listings
|   |   |   |— menu
|   |   |   |— overlay
|   |   |— irisrda_templates
|   |— systemd /* service files */
|   |— profile.d /* shell script files */
|   |— rc.d
|   |   |— init.d /* rc files */
|   |— logrotate.d /* logrotate conf files */
|— srv
|   |— iris_data
|   |   |— ingest /* IRIS ingest files */
|   |   |— product /* IRIS derived product files */
|   |   |— product_raw /* IRIS RAW (packed ingest) files */
|   |   |— tsarchive /* saved IQ data */
|   |   |— tape_inv /* tape backup metadata */
|   |   |— ascope /* Data saved from ascope utility */
|   |   |— suncal /* Sun based calibration utility data */
|   |   |— temp /* temp storage */
|   |   |— zdrCAL /* ZDR calibration utility data */
|— usr
|   |— libexec
|   |   |— vaisala
|   |   |   |— pipes /* pipes from data_converters */
|   |   |   |— irisrda /* scripts for irisrda */
|   |— bin /* executables for irisrda */
|   |— share
|   |   |— X11 /* app defaults resource files */
|   |   |— nls /* po files */
|   |   |— vaisala
|   |   |   |— irisrda
|   |   |   |   |— icons /* icon files */
|   |   |   |   |— sounds /* sound files */
|   |   |   |   |— keys /* key files */
|   |   |   |— doc /* user documentation, release notes and license files */
|   |— lib64 /* all libraries */
|   |— include
|   |   |— vaisala/* all header files */

```

```
└─ var
  └─ log
    └─ irisrda /* all log files */
  └─ spool
    └─ vaisala-io
      └─ input /* Default IRIS input directory */
      └─ output /* Default IRIS output directory */
      └─ raw
      └─ volume
      └─ temp /* Conversion pipes temp storage */
```

3. Preparing for installation

3.1 Hardware recommendations

Vaisala recommends using a server computer that meets the following specifications:

Feature	Recommendation
Drive size	512 GB SSD configured with RAID 1 (mirrored)
Memory	16 G of DDR4 Memory
CPU	2 XEON E5-2609 v3 Processors with 6 Cores, 1.9 GHz clock speed, 6.4GT/s QPI Speed, 15M of Cache

The server provided by Vaisala meets these recommendations.

3.2 Installation image options

This version of IRIS RDA software requires the AlmaLinux 9 operating system.

Vaisala provides customized ISO images for AlmaLinux and IRIS/RDA software on the Vaisala FTP website:

<https://ftp.sigmet.vaisala.com/files/releases>

ISO Image	Notes	Instructions
Combined AlmaLinux OS and IRIS/RDA sw ISO image	Automatically installs both the AlmaLinux operating system and the IRIS/RDA software. Available on USB drive and FTP site. You can also use this image to only install the IRIS/RDA software.	Installing OS together with IRIS/RDA: Chapter <i>Installing IRIS/RDA and AlmaLinux with Kickstart</i> Installing only IRIS/RDA: Chapter <i>Installing IRIS/RDA software</i>
IRIS/RDA software as standalone ISO image	This image is smaller than the combined ISO image, so it is faster to download. Available on the FTP site.	Chapter <i>Installing IRIS/RDA software</i>
AlmaLinux operating system as standalone ISO image	This image is smaller than the combined ISO image, so it is faster to download. Available on the FTP site.	Appendix <i>Installing AlmaLinux</i>

When installing the IRIS/RDA standalone ISO, you can select either online or offline installation. The online option enables access to RPMs from remote repositories that are needed if the host system does not contain dependencies that come from **AppStream** and **BaseOS** repositories. These repositories are automatically included when the combined OS and software ISO image used. The online installation requires Internet connection.

If you select the offline installation option, the installation only uses the repositories provided by ISO image and does not try to access remote repositories. In this case, for example, **devel** packages cannot be installed, because they require a specific version of base packages and this requires accessing remote repositories.

4. Upgrading AlmaLinux 8.7 to AlmaLinux 9

This upgrade process is intended for a system that is running AlmaLinux 8.7 and connected to Internet. For information on an offline migration upgrade, see AlmaLinux wiki website <https://wiki.almalinux.org/elevate/Elevate-offline-guide.html>.

- ▶ 1. Log in as **admin**.
- 2. Backup IRIS RDA configurations:

```
sudo systemctl stop iris rcp8 rvp antennad
cd to /etc/vaisala
sudo tar -zcvpf ~/config.tgz irisrda/
```

- 3. Uninstall the IRIS RDA rpms and dependencies:

```
sudo dnf -y remove vaisala*
sudo dnf -y remove kmod-kvaser* rda-kmod
sudo rpm -e lua --nodeps
```

- 4. Import the rpm GPG key:

```
sudo rpm --import https://repo.almalinux.org/almalinux/RPM-GPG-KEY-AlmaLinux
```

- 5. Update to the latest software:

```
sudo dnf -y update
```

- 6. Reboot the system:

```
sudo reboot
```

- 7. Install the elevate-release package:

```
sudo yum install -y http://repo.almalinux.org/elevate/elevate-release-
latest-el$(rpm --eval %rhel).noarch.rpm
```

8. Install *leapp* packages:

```
sudo yum install -y leapp-upgrade leapp-data-almalinux
```

9. Modify the firewall configuration:

```
sudo sed -i "s/^AllowZoneDrifting=.*\/AllowZoneDrifting=no/" /etc/firewalld/
firewalld.conf
```

10. Run a pre-upgrade test:

```
sudo leapp preupgrade
```

If the test passes, proceed to the upgrade.

11. Run the upgrade:

```
sudo leapp upgrade
sudo reboot
```

12. Check the migration results:

```
cat /etc/redhat-release --
```

This command should now print out: "AlmaLinux release 9.4 (Seafoam Ocelot)".

13. After the successful upgrade:

a. Remove all packages from the exclude list:

```
sudo dnf config-manager --save --setopt exclude='
```

b. List the EL8 and in-place upgrade rpms:

```
rpm -qa | grep -e '\.el8' | grep -vE '^(gpg-pubkey|libmodulemd|katello-  
ca-consumer)' | sort
```

c. Remove the rpms manually with the `dnf` command:

```
sudo dnf remove leapp-*  
sudo dnf remove kernel*el8*
```

d. List and disable the DNF repositories whose packages are not AlmaLinux 9 compatible:

```
dnf repolist  
sudo dnf config-manager --set-disabled <repo-id>
```

where `<repo-id>` is your repository ID.

e. Check if there are any remaining EL8 rpms, and remove them with `dnf` command.

14. Check upgrade logs:

```
cat /var/log/leapp/leapp-report.txt  
cat /var/log/leapp/leapp-upgrade.log
```

Remove these logs after reviewing them.

The operating system upgrade is now ready, and you can install the IRIS RDA software. After the installation, you can restore the configurations from the backup file, if needed:

```
sudo tar -zxvpf <path to backup file> -C /etc/vaisala/
```

5. Installing IRIS/RDA and AlmaLinux with Kickstart

5.1 Creating installation media


After creating and initializing the installation media, you can run the installation process.

5.1.1 Creating USB installation media on Windows

These instructions apply to Windows 10 and Windows 11.


When creating USB installation media on Windows, use a standalone program such as **rufus** (available at <http://rufus.akeo.ie/>). Follow the on-screen instructions.

- ▶ 1. Launch **rufus** by double-clicking the program icon.
2. Insert a USB drive in the USB port.
3. Select the drop-down list to the right of the **Create a bootable disk using**, and select **ISO Image**.



4. Select the **Disc** icon and then select the iso image.

5. Select **Write in DD Image mode** if a warning for the hybrid ISO image is displayed.



6. Select **Close**.

5.1.2 Creating USB installation media on Linux (AlmaLinux)



NOTICE! This operation destroys data on the device you operate on.

1. Run `$ lsblk` to list block devices on your system. Take note of the output.
2. Insert a USB drive in the USB port.
3. Run `$ lsblk`.
Compare the output to the previous step. The additional block device from this output is your USB drive.
4. Run `$ dd if=path/toAlmalinux.iso of=/dev/xxx`
Where `/dev/xxx` is the path to the USB drive. Do not use the partition number for the USB drive.
For example: `/dev/sdc`.

5.2 Running the installation with Kickstart

1. In the AlmaLinux window, select **Install AlmaLinux 9.4**, and press **Enter**.



NOTICE! Do not use the option **Test this media & install AlmaLinux 9.4**. It skips the configuration process.

```
AlmaLinux 9.4

Install AlmaLinux 9.4
Test this media & install AlmaLinux 9.4

Troubleshooting >

Press Tab for full configuration options on menu items.
```

2. When prompted, configure the hostname and IP address.


```
Enter Hostname: new-radar

===== Configuring for enp0s3 =====
Do you want to configure this interface? [y/n] y
Configure as static (default is DHCP)? [y/n] n

===== Configuring for enp0s8 =====
Do you want to configure this interface? [y/n] y
Configure as static (default is DHCP)? [y/n] y
Enter IP address: 10.0.2.1
Enter netmask: 255.255.255.0

===== Configuring for enp0s9 =====
Do you want to configure this interface? [y/n] y
Configure as static (default is DHCP)? [y/n] y
Enter IP address: 10.0.3.1
Enter netmask: 255.255.255.0
```

3. In the **Installation Summary** window:
 - a. Select **Keyboard** and select the desired keyboard version.
 - b. Select **Time & Date** and set the time and date.




4. In the **Installation Summary** window, select **Software Selection**.
5. In the **Software selection** window, select **Server with GUI** and the software you want to install.

By default, **IRIS**, **RCP8**, **RVP10**, and all data converter RPMs are selected.

For more information on the options, see [Running the installation script \(page 28\)](#).

6. In the **Installation Summary** page, select **Begin Installation**.




The installation process begins.

7. When the installation is complete, the system will reboot automatically.

5.3 First login and password change

The IRIS RDA software installation creates three default user accounts: **radarop**, **observer**, and **admin**.

After installing IRIS RDA from installation media, the default password is **xxxxxx**. Changing this password on the first login is mandatory.



NOTICE! If you do not change the **xxxxxx** password, you will be locked out of the system.

- ▶ 1. Select the **radarop** login icon.
- 2. Enter the default password.
- 3. Change the password.
- 4. Do the same for the other default user accounts (**observer** and **admin**).

5.4 Enabling login as **root** for using IRIS Focus

If you are installing IRIS Analysis and IRIS Focus on the same server, you need to enable logging in as **root**.

1. Log in as **admin** user.
2. Type:

```
$sudo passwd root
```

3. Follow the prompts.

```
[admin@wrs200 ~]$ sudo passwd root
Changing password for user root.
New password:
Retype new password:
passwd: all authentication tokens updated successfully.
[admin@wrs200 ~]$ █
```

4. Log out, and log in as **root**.

5.5 Verifying that the services are running

1. If you have not done so already, log in as **radarop**.

- In the terminal window, list the services currently running by typing:

```
# ps_iris
```

The **COMMAND** column lists the running services.

Option	Running services
-rvp10	rvp10
-rcp8	rcp8

You may also see that the antenna (**ant_***) and receive (**rtd_***) processes have started.



IRIS does not start until you have installed the IRIS license.

More information

- [ps_iris command \(page 79\)](#)

5.6 Configuring IRIS license setups




Figure 1 License setup example

Before you can use IRIS/RDA software, you must request and set up a license.

1. Open the **Setup** utility by typing:

```
setup&
```

2. In the **Setup** utility, select **License**.
 - a. Delete the default texts in the **License** fields.
 - b. Depending on your setup, for **IRIS Style**, select either **Radar** or **Analysis**.
 - c. In **Site name**, type a name for the machine (typically the host name of the machine).
For example: **hel-radar**
 - d. In **Site code**, type a code name for the radar site.
For example: **HEL**
 - e. In the **IRIS License Setups** window, select **File > Close**
 - f. Select **File > Save** and **File > Exit**.
3. In the terminal window, type: **show_machine_code**
The terminal prints the licensing information about this machine. For example:

```
-----  
Licensing Information for IRIS Version 10.2.0  
-----
```

```
Machine Code: EMNTRK  
Site Name: hel-radar  
Check Code: WPEFXE  
OS Name: Linux  
OS Release: 3.10.0-229.el7.x86_64  
Host Name: localhost.localdomain  
Locking To: host
```

4. Copy all the information under **Licensing Information for IRIS Version <version number>**
5. Contact your Vaisala representative and request an IRIS license.
Provide the information you copied in the previous step.
6. When you receive the license from Vaisala, return to **Setup > License** and type the **License 1, License 2, ... license codes in the order listed in the license**.
Depending on your configuration, you may have codes such as:
 - IRIS Features Code
 - IRIS Product Code
 - RDA Features Code
7. Select **File > Save** and **File > Exit**.

8. To confirm that your license is correctly setup, start IRIS by typing:

```
siris
```

Check that the IRIS **Quick Look Window** starts.

If the IRIS **Quick Look Window** does not start, see Troubleshooting instructions.

6. Installing IRIS/RDA software (standalone)

6.1 IRIS/RDA installation overview

Installing the IRIS/RDA software from the installation media with a script involves the following steps. The steps are described in detail in the following chapters.

- ▶ 1. Install the AlmaLinux operating system according to Appendix *Installing AlmaLinux*.
2. Log in as **root**.
See [Logging in as root \(page 26\)](#).
3. Install the IRIS / RDA installation media, and verify that it mounts.
See [Mounting the installation media and verifying the mount point \(page 26\)](#).
4. Open a terminal window.
5. Run the installation script.
6. Verify that the expected services have started.
See [Verifying that the services are running \(page 21\)](#).
7. Configure your licenses.
See [Configuring IRIS license setups \(page 23\)](#).
8. Check and update your firmware as needed:
 - [Installing IO-62 firmware \(page 43\)](#)
 - [Installing RVP10 \(RDA\) firmware \(page 45\)](#)

6.2 Logging in as root

- ▶ 1. In the login screen displaying your user accounts, select **Not Listed?** below the user account login box.
2. Enter **root** as the user name and your root password.
The system displays a welcome message after the first time you log in and a blank screen after other logins.
If prompted, select your language and input settings.

You can now continue with the IRIS/RDA software installation.

6.3 Mounting the installation media and verifying the mount point

The IRIS/RDA installation media can be either a USB drive or a DVD disc.

- ▶ 1. Install the USB drive in the USB port of the server, or install the DVD disc in the DVD drive.
- 2. If you are using a DVD drive, a small black window indicates that the DVD disc has been recognized.
Select **X** in the upper right corner to close the window.
- 3. Verify that the installation media is recognized with the mount point by typing:

```
df
```

The installation media should be listed with the mount point in `/run/media/root/irisrda_X.XX.X`, where `X.XX.X` is the version of software you are installing.

- 4. If you do not see the installation media listed, try the following:
 - Insert the USB drive to a different port
 - Run the **lsblk** command to see if the installation media shows on the list. If it shows, mount it manually with the command:


```
mount -o loop dev/<usbdevice> /mnt
```

, where **usbdevice** is the name of the USB drive from the `lsblk` list.
In the case of a DVD, replace **<usbdevice>** with the DVD from the `lsblk` list.

6.4 Opening a terminal window

- ▶ 1. In the upper left corner, left-click **Activities**.

2. Either type **terminal** in the search field on top of the window, or click on the terminal icon at the bottom of the screen.



A terminal window with a prompt opens.

3. Remove the user you created during the operating system installation.

For example, if you created the user **service**, type:

```
# userdel -r service
```

6.5 Running the installation script

The *vaisala-iris-rda-install.sh* script automatically performs all the processes that make the system ready to run. For example, the script installs the requested products with their dependencies, creates directories, and configures paths and users.

The script also sets up a local repository that is required for installing upgrade packages via DNF.

- ▶ 1. Change to the directory where the IRIS/RDA installation media is mounted.
For example, if the mounting point is `/run/media/root/irisrda`, type:

```
# cd /run/media/root/irisrda
```

2. Run the installation script with desired parameters by typing:

```
./vaisala-iris-rda-install.sh <parameter>
```

, where **<parameter>** can be any of the following:

- `--help`: Prints out the applicable parameters.
- `--iris`: Installs IRIS on a running system (with all dependencies, including **common** package).
- `--rcp8`: Installs RCP8 on a running system (with all dependencies, including **common** and **rda** packages).
- `--rvp9`: Installs RVP9 on running system (with all dependencies, including **common** and **rda** packages).
- `--rvp10`: Installs RVP10 on a running system (with all dependencies, including **common** and **rda** packages).



`--rvp9` and `--rvp10` options cannot be used at the same machine.

- `--converter "<converter_name> <converter_name> <converter_name> ..."`: Installs **data-converters-<converter_name>** on running system (with all dependencies, including **common** package). Accepts converter list inside quotes as argument. The option `--help` shows all converter names that can be installed with the script.
- `--online`: provides access to remote repositories that is set up on system.
- `--offline`: forces the script to use the repositories provided by the ISO image. No access to remote repositories.
- `--with-os`: If you want to point the external DVD ISO for dependencies that come from AppStream and BaseOS, provide the mount path of the AlmaLinux DVD. Providing `--os-media` may be useful if third party dependencies are not already installed on your system and installation image does not include those dependencies when you are running the offline installation.

3. Reboot the system to apply changes and to run enabled services:

```
reboot
```

6.6 First login and password change

The IRIS RDA software installation creates three default user accounts: **radarop**, **observer**, and **admin**.

After installing IRIS RDA from installation media, the default password is **xxxxxx**. Changing this password on the first login is mandatory.



NOTICE! If you do not change the **xxxxxx** password, you will be locked out of the system.

- ▶ 1. Select the **radarop** login icon.
- 2. Enter the default password.
- 3. Change the password.
- 4. Do the same for the other default user accounts (**observer** and **admin**).

6.7 Verifying that the services are running

- ▶ 1. If you have not done so already, log in as **radarop**.
- 2. In the terminal window, list the services currently running by typing:

```
# ps_iris
```

The **COMMAND** column lists the running services.

Option	Running services
-rvp10	rvp10
-rcp8	rcp8

You may also see that the antenna (**ant_***) and receive (**rtd_***) processes have started.



IRIS does not start until you have installed the IRIS license.

More information

- ▶ [ps_iris command \(page 79\)](#)

7. Upgrading IRIS and RDA software

7.1 IRIS RDA upgrade overview

This chapter describes how to upgrade from IRIS/RDA 10.x to later releases.

The upgrade is handled by the DNF package manager installed by the IRIS 10.1 installation script. In the upgrade process, the DNF replaces existing RPMs with new RPMs.

The upgrade process includes the following steps:

- ▶ 1. Back up your configuration files. See [Preparing for the upgrade \(page 31\)](#).
- 2. Get the latest software release ISO image and *Release Notes* at <https://ftp.sigmet.com/files/releases/>. See [Getting upgrade software \(page 32\)](#).
- 3. Run the upgrade installation script. See [Running the upgrade script \(page 33\)](#).
- 4. Run the **Setup** utility. See [Running Setup after upgrade \(page 34\)](#).

7.2 Preparing for the upgrade

- ▶ 1. Log in as **root**.
See [Logging in as root \(page 26\)](#).
- 2. Back up and save important configuration files.
As part of the upgrade, many files are erased and replaced. However, the upgrade procedure preserves everything in `${IRIS_CONFIG}`.
 - a. Back up and save customized configuration files.
 - b. Even though this file is not overwritten during the upgrade, create a backup of `/etc/vaisala/irisrda`:

```
# cd /etc/vaisala/
# tar cfz <config_nodename_date.tgz> irisrda/
```

- c. To back up the whole installation (for example, to support rollback), back up `/etc/vaisala`:

```
# cd /etc/
# cp -R vaisala/ sigmet_versionNumber/
```

3. Print the current setup.

Run the **Setup** utility on the old system, and generate an ASCII listing file with the **File/List** command.

The format of these files can change between software versions, so you may need to re-enter some information.

A date coded listing file is generated in the `${IRIS_LISTING}` directory, typically in `etc/vaisala/irisrda/listings`.

4. Make sure all applications are stopped by exiting any IRIS/RDA utilities that you are running and typing the command:

```
$ qiris
```

5. Verify that all processes have stopped by typing:

```
ps_iris
```

6. Stop any running processes as **root** with the **kill <process ID number>** command.

The process ID number is the first column of numbers from the `ps_iris` output.

7.3 Getting upgrade software

New features and updates are provided as software upgrades from the following sources:

- FTP download
Connect to the Vaisala Sigmet server in <ftp.sigmet.vaisala.com>.
 - If using a web browser, navigate to `/files/releases/<latest version>`
 - If using an FTP client, navigate to `/outgoing/releases/latest version>`

These public releases are free of charge, but do not include support services unless you are under warranty or have purchased a support contract from Vaisala. Contact your Vaisala representative to arrange a support contract.

- USB drive or DVD disc
Provided as part of a support contract or upon request.

7.3.1 Downloading upgrade files



The examples in this procedure use release 10.1.0 as an example. In most cases, you install the most recent version, labelled below as `<X.XX>`.

- ▶ 1. Create a directory named `/tmp/iris-<X.XX>`.

2. If you are downloading RDA software, create a directory named `/tmp/rda-<X.XX>`.
You should make a separate directory for each version and type (IRIS/RDA) of software that you download.
3. Login as **radarop**.

```
$ cd /  
$ mkdir /tmp/rda-10.1.0
```

4. Change to the `/tmp` directory by typing:

```
$ cd /tmp/rda-10.1.0
```



On Windows machines, you can type the commands in the command prompt (remember to use the `"\"` backslash for DOS).

5. Start the FTP browser.
6. In the directory listing of available releases, find your release.
7. Download the `irisrda_image.iso`.
Download the appropriate software image according to OS version (AlmaLinux 8, AlmaLinux 9).

7.4 Running the upgrade script

This instruction assumes that the operating system stays the same.

- ▶ 1. Log in as **admin**.
2. Mount the ISO image:

```
sudo mount -o loop <iso-image> /mnt
```

3. Change the directory to `/mnt`:

```
(cd /mnt)
```

4. Run the command:

```
sudo dnf upgrade -y --allowerase --nogpgcheck --disablerepo="" \
--repofrompath vaisala-local,$(pwd)/vaisala-iris-rda \
--repofrompath vaisala-extras-local,$(pwd)/vaisala-iris-
rda-extras \
vaisala-wr-*
```

7.5 Running Setup after upgrade

After upgrading, the **Setup** utility fills in default values for any new settings that were added. Vaisala recommends reading the *Release notes* document and then checking the new settings to make sure they are right for your system.


1. Login as **radarop**.
The default password is: **Va1sa1a!**
(Note that the first character is capital letter 'V', and the third character is number one '1'.)
2. Launch the **Setup** utility.
At startup for an upgrade, **Setup** checks the parameters to verify that they are within reasonable bounds and lists any problems.
The listing gives the name of the variable in question and prompts the user to consider the repair command. Errors are usually related to new features that have not been addressed or outdated features that do not conform to the current upgrade.
3. In the list dialog, select **Repair** to replace any mismatches with the appropriate default.
4. If you receive errors related to customized fields that are important to your operation, see [Invoking Setup and built-in error checking \(page 34\)](#).

7.5.1 Invoking Setup and built-in error checking

When IRIS starts, it performs configuration and bounds checks.

For new users, the **Setup** parameters are typically correctly set and do not cause any configuration errors. If an error does occur, follow these steps.

- ▶ 1. In the terminal window, type: **setup&**
The **Setup** utility launches.



There are 2 variants of the **Setup** utility: one for IRIS and one for the RDA (RVP signal processor or an RCP8 antenna controller). The RDA variant does not show the IRIS setup features.

2. Select the part of the system setup you want to check or configure.
 3. Make your changes and close the window for the selected part of the system.
 4. Select **File > Save**.
- The configuration files are now updated.
5. To create a listing file of the **Setup** configuration:
 - a. Select **File > List**.

A listing file called `YYYYMMDDHHMM.setup` is created in the `${IRIS_LISTINGS}` directory.

6. To take the configuration changes into effect, restart the application:
 - a. For changes made to the **Setup > IRIS** section, restart the IRIS daemons by typing:

```
qiris
siris
```

- b. For changes to the **Setup > RVP** section, stop any running utilities with the command `systemctl stop <service unit>`, for example:

```
systemctl stop iris rvp10 rcp8
```

- c. Restart the utilities with the command `systemctl start <service unit>`, for example:

```
systemctl start iris rvp10 rcp8
```

RVP has a configuration state accessible through **dspx**. Part of that state is local to the processor and part of it is also visible in **Setup > RVP**.

- d. For changes to the **Setup > RCP** section, in addition to the above, you must stop RCP8 (if you have one), and stop the antenna daemons, by typing:

```
$ qiris
$ sudo systemctl stop rvp10
$ sudo systemctl stop rcp8
$ qant
$ sudo systemctl start rcp8
$ sudo systemctl start rvp10
$ siris
```

RCP8 has a configuration state accessible through **Antx**. These changes take effect when you return to the top level prompt. You must save your changes.



License changes can affect RVP and IRIS.

7. If an error list is displayed,
 - a. Check the error list for parameters that you have customized and correct these customizations.
 - b. Select **Repair** to make corrections that are necessary for the software but do not need to be customized for your operation.
 - c. Select **File > Save**.

7.6 Checking the kernel module status

After installation or upgrade, check that the RDA kernel module has been installed and loaded. If the kernel module has not been loaded, the rvp10 process will not start.

To check this, type:

```
lsmod | grep rda
```

If no data is displayed, the kernel module has not been loaded or installed properly.

To check the status of the kernel module, type:

```
systemctl status systemd-modules-load.service
```

If the kernel module is not running, start the module by typing:

```
systemctl start systemd-modules-load.service
```

8. Configuration

8.1 Configuring RDA software

After the receiving your unit from the factory, or after software re-installation, you must configure the software to customize your system for your environment and application.

Table 2 RDA configuration tools

Configuration tool	RDA device	Description
setup/RVP utility <i>setup_dsp.conf</i> See <i>IRIS and RDA Utilities Guide (M212925EN)</i> .	RVP10	Configures the local environment required to run RVP support utilities such as Ascope and dspx . Examples: radar equation parameters that are required for calibration, pulse width definitions, and PRF request limits.
setup/RCP utility <i>setup_ant.conf</i> See <i>RVP10 User Guide (M212604EN)</i> .	RCP8	Configures the local environment required to run the RCP8 support utilities that such as Antenna or Bitex . Examples: max allowed AZ/EL velocity request, MIN and MAX elevation angles that can be requested, and LAT/LON of radar for sun tracking.
RVP10 NV setups <i>rvp10.conf</i> See <i>RVP10 User Guide (M212604EN)</i> .	RVP10	Defines the details of the sampling and processing algorithms, as well as the operational configuration of the system. Examples: IF filter design and selection, PRF limits, relative trigger timing, dual-polarization features.
RCP8 NV setups <i>rcp8.conf</i> See <i>RCP8 User Guide (M212923EN)</i> .	RCP8	Configures which status and control bits are available and define the antenna servo control parameters. Examples: physical or virtual tachometer selection, shutdown safety criteria and internal antenna simulator on/off.
<i>profile.conf</i> See <i>RVP10 User Guide (M212604EN)</i>	RVP10	Configures the network interface from RVP10SRV server to IFDR10.
<i>softplane.conf</i> See <i>RVP10 User Guide (M212604EN)</i>	RVP10 RCP8	Defines the I/O signals on the I/O-62 connector panel, pin-by-pin. Examples: whether a line is an input or output, electrical specification such as RS422 or TTL, what local variable name is associated with each line.



During installation, you must configure the **Setup** utility and the TTY setups for your system.

The configuration results are stored as ASCII text *.conf* files, typically in the */etc/vaisala/irisrda* directory. Each file has a factory default configuration file that is stored in the template directory. The default is:

```
/etc/vaisala/irisrda/templates/init/
```



For a radar network with identical hardware, you can perform configuration maintenance by copying pre-tested files over the network.

8.2 Configuring firewall

By default, the firewall is configured to be active in the AlmaLinux installation. However, some modifications are needed to enable communications between units. NTP service is added to firewall configuration by RVP10 post-install script. Additionally, WRM200 factory configuration disables firewall on IFDR10 and radar cabinet network interfaces. WRS300 and WRS400 factory configuration disables the firewall on radar cabinet network (IFDR is in the same network).

8.2.1 Configuring the firewall

IRIS Focus connects to IRIS Analysis using port 30735. By default, the firewall of the IRIS Analysis server blocks this port. When IRIS Analysis and IRIS Focus are installed on separate servers, you need to configure IRIS Analysis server to allow the connection to this port:

- ▶ 1. Log in to the IRIS Analysis server as **admin**.
2. Run the following commands:

```
sudo firewall-cmd --add-port=30735/tcp --permanent
sudo firewall-cmd -reload
```

8.2.2 Configuring the IFDR10 interface

On the interface to IFDR10, the firewall should be disabled. To do this, move the interface to the trusted zone. IFDR10 also needs the **ntp** service. It can be added to the allowed services.

- ▶ 1. Use the following commands:

```
sudo firewall-cmd --zone=trusted --change-interface="rvp10_interface" --
permanent
sudo firewall-cmd --add-service=ntp --permanent
sudo firewall-cmd --reload
```

In the command, replace `rvp10_interface` with the real interface name. You can find the interface name by looking for the network interfaces in radar server. In the following example, we know that RVP10 is connected to 10.0.3.x network, and from the listing below we see that the name for that interface is **ens6f1**.

```
$ ip address
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group
default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        .....
4: ens6f0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc mq state
DOWN group default qlen 1000
    link/ether 04:42:1a:1d:7d:3a brd ff:ff:ff:ff:ff:ff
    altname enp59s0f0
5: ens6f1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP
group default qlen 1000
    link/ether 04:42:1a:1d:7d:3c brd ff:ff:ff:ff:ff:ff
    altname enp59s0f1
    inet 10.0.3.1/24 brd 10.0.3.255 scope global noprefixroute ens6f1
        valid_lft forever preferred_lft forever
```

8.2.3 Radar cabinet interface

Typically, the radar cabinet network interface can be moved to the trusted zone. Use the following command and replace `radar_cabinet_interface` with the real interface name. To find the interface name, look for the network name of the radar cabinet network (typically, 10.01.x and 10.0.2.x networks).

```
sudo firewall-cmd --zone=trusted --change-interface="radar_cabinet_interface"
--permanent
sudo firewall-cmd --reload
```

8.2.4 Remote IRIS menu interface

To be able to connect to the radar server IRIS from the remote IRIS menu, the firewall must be configured to allow all traffic from selected IP addresses. In the following command, replace `<IP_ADDRESS>` with the real IP address of the IRIS machine connecting to radar.

```
sudo firewall-cmd --zone=trusted --add-source=<IP_ADDRESS> --permanent
sudo firewall-cmd --reload
```

VNC connections to radar server

If you want to use a VNC connection to the radar server, you need to allow the `vnc-server` and selected ports through the firewall. You can check the services using the following command:

```
$ sudo firewall-cmd --list-services
cockpit dhcpv6-client ntp ssh vnc-server
```

Add allowed services using the following commands:

```
$ sudo firewall-cmd --add-service vnc-server --permanent
$ sudo firewall-cmd --reload
```

Additionally, you must open the ports used by VNC. As an example, if **TigerVNC** server is started in port 5, you need to open port 5905. The default port for **TigerVNC** is 5900, and when an additional port N is configured, the firewall port 5900+N must be opened. In the example, a range of ports is opened, too.

```
$ sudo firewall-cmd --add-port=5905/tcp --permanent
$ sudo firewall-cmd --add-port=5910-5920/tcp --permanent
$ sudo firewall-cmd --reload
```

Allowed ports can be checked by the following command:

```
$ sudo firewall-cmd --list-ports
```

8.3 Configuring SSH

You must set up an ssh connection from one computer (the **host**) to another (**target**) so that users can login from **host** to **target** without a password, and IRIS can send data from the **host** to the **target**.

- ▶ 1. Log in to the host computer as **admin**.
- 2. Check if `.ssh` directory exists.

If not, then create the directory by typing:

```
sudo ssh-keygen -t dsa
```

When prompted with questions, press **Enter** without typing anything.

- 3. Type:

```
sudo ssh-copy-id -i id_rsa.pub radarop@remotehost
```

- 4. When prompted for login, enter the **radarop** password.
- 5. After a successful login, log out again.
- 6. On the host computer, test the SSH connection as **admin** with the command:

```
sudo ssh radarop@remotehost date
```

You should get the date and time display from the remote host without a password prompt.

You can now send data from the **host** computer to the **target** through the IRIS product output menu.

9. Installing IO-62 firmware

If you have installed or upgraded the RDA software, and your system includes an IO-62 card and connector panel, you must update the firmware running on RCP8 to be compatible with the installed RDA software.

- ▶ 1. Login as **admin**.
- 2. Check for running processes by typing:

```
sudo ps-iris
```

- 3. Stop any running processes by typing:

```
sudo qiris
sudo quant
```

- 4. Log in as **radarop** (default password **Va1sala!**).
You enter X-Windows.
- 5. Right-click and start a terminal window.
- 6. For each Vaisala component, type the appropriate command. For example:

Vaisala component	Command
Standard I/O-62 card	io62-0
Standard connector panel	io62cp-0

- 7. Shut down the system by typing:

```
poweroff
```

- 8. When **Power down** is displayed, turn power off with power switch on lower right of front panel.

The FPGA software installation is complete.

- 9. Reboot the unit.

Follow the progress of the reboot on the monitor. The front panel LED display shows the time of the reboot and display diagnostic messages.

The reboot takes about 1 minute.

10. Stop the RCP process by typing:

```
$ killall rcp8
```

11. Run the following diagnostics and observe the results:

```
$ rdadiags io62-0  
$ rdadiags io62cp-0
```

12. Restart the RCP8 process by typing:

```
rcp8 &
```

13. Verify that the restart messages show no faults.
14. Configure RCP.

See *RCP8 User Guide (M212923EN)*.

10. Installing RVP10 (RDA) firmware

Before installing RVP10 (RDA) firmware, make sure that:

- The second Ethernet port has been configured. See [Configuring the system and network \(page 65\)](#).
- IFDR10 is physically connected to the port.

If you have installed or upgraded the RDA software, you must update the firmware running on IFDR10 to be compatible with the installed RDA software.

1. Reboot the computer.
2. Login as **radarop**.

The default password is: **Va1sa1a!**

(Note that the first character is capital letter 'V', and the third character is number one '1'.)

3. If IRIS / RDA services are running, turn them off.
 - a. Check what is running.

```
# ps_iris
```

- b. If any services are running, stop them.

```
# systemctl stop iris
# systemctl stop rvp10
# systemctl stop rcp8
# systemctl stop dspexport
# systemctl stop antennad
```

4. Verify that all services have stopped:

```
# ps_iris
```

If there are services running, stop them using the **systemctl** commands or manually kill them.

You must be logged in as **root** to use the **kill** command:

```
# su
# kill <process ID number>
```

5. If not powered, power on IFDR10, and wait for it to boot.
6. If the network cable is not attached, attach IFDR10 to the second Ethernet connection configured for the 10.0.3.x network.
7. Verify that IFDR10 is accessible over Ethernet.

Run `ping` letting at least 4 packets transmit, and press **Ctrl+C** to exit program. Verify that there is 0% packet loss.

```
# ping 10.0.3.254
```

10.0.3.254 is the default IP address of IFDR10.

8. Change to the repository where the image is installed (be default `/usr/bin`):

```
cd /usr/bin
```

9. Use the **rdaflash** utility to update the IFDR10 firmware:

```
rdaflash -ifdr10
```

This takes several minutes. Do not interrupt programming.



NOTICE! When programming starts, do not power cycle or reboot IFDR10 until **rdaflash** is successfully completed.

```
radarop@radar_rvp10> rdaflash -ifdr10
Open connection ... done.
Upload firmware ... done.
Stage=INITIALIZING Completed= 0% Error=''
Stage=INITIALIZING Completed= 0% Error=''
Stage=LOADING Completed= 10% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 40% Error=''
Stage=INSTALLING Completed= 95% Error=''
Stage=COMPLETED Completed=100% Error=''
Activate new firmware ... done.
radarop@radar_rvp10>
```

When the programming is complete, IFDR10 reboots.

10. Reboot the computer and login as **radarop**.
11. Verify that the expected process are running with the command:

```
# ps_iris
```

12. Configure RVP.

See *RVP10 User Guide (M212604EN)*.

13. If the upgrade is interrupted or not completed successfully, the unit stays in diagnostic mode on the next reboot so you can recover from the failure.

14. For RVP upgrades, if the RDA software boots, but is unresponsive, you can force the RVP into diagnostic mode by sticking a paper clip in the inner most hole on the side of the enclosure.

After entering the diagnostic boot mode, you can re-flash the IFDR10 software from the signal processor to recover from a corrupted image.

If the IFDR10 firmware upgrade is part of a software upgrade process, see [Running Setup after upgrade \(page 34\)](#).

11. Login, logout, and shutdown

11.1 Powering up

When you power-up the computer, the system goes through an automatic startup of the operating system at the end of which the software starts and performs power-up self tests.

If you are not doing any diagnostic or software maintenance work on the system, there is no need to log-in after power-up. When you turn the unit on, your application software takes over.

11.2 Local and remote login

You can login either locally or remotely.

- Login locally using the local workstation or through a KVM.
- You can login remotely if `ssh` is enabled. Check with your network administrator.

Here, we assume a local login is used.

11.3 Default usernames and passwords

The standard software installation defines the following standard users:

- **radarop**
- **observer**
- **admin**

For servers installed at Vaisala, the default password is: **Va1sa1a!**

(Note that the first character is capital letter 'V', and the third character is number one '1'.)

For security reasons, changing the password is strongly recommended.

To run commands that require **root** privileges, log in as **admin**, and type **sudo** at the beginning of the command.

The system administrator can change passwords using the standard Linux password support.

11.4 Running commands with root privileges

IRIS RDA software does not include a **root** account. To run commands that require **root** privileges:

1. Log in as **admin**.
For servers installed at Vaisala, the default password is: **Va1sa1a!**
2. Type **sudo** at the beginning of the command.

11.5 Local login as operator after powerup

- ▶ 1. At the power-up login prompt, type **radarop** and press **Enter**.
When prompted, provide the password (default password is **Va1sa!a!**).
An X-Window screen appears.
- 2. Right-click and select **New Window** to get a terminal window.
The top of the terminal window shows your user name, the node name of the system, and the current directory path.

11.6 Powering off

- ▶ 1. Type **poweroff**.
The system goes through a shutdown sequence. When it is done, **Power down** is displayed.

12. Troubleshooting

12.1 Correcting file ownership and protection

Sometimes, when starting a program or trying to access calibration files, users cannot access some files or they receive an error message saying they do not have privileges to do an operation.

This is because the file ownership and protection settings are incorrect.



Do not change the file protection manually. Always use the `sigmet_env -setown` command to fix the protection of your files.

1. To correct the file ownership and protection, type:

```
# sigmet_env -setown
```

The script goes through the `/etc/vaisala` directory tree, changing the ownership of the files to **operator** and setting the protection as follows:

- Directories—`rw-rwxr-x`
- All files, except executable files—`r-rw-r--`
- Executable files—`rwsrwsr-x`

12.2 Authorizing remote X-Windows on your node

1. To enable IRIS systems running on other nodes to send output to your screen, enter the command:

```
$ xhost +<host>
```

Where `<host>` is the remote hostname, or IP address.

2. Check that this works as you intend.
3. Add the appropriate command at the end of one of the following files:
 - To authorize the windows as soon as anyone logs in: `/etc/profile.d/sigmet.sh`
 - To support just one user authorizing the windows: home directory `.bash_profile`

12.3 Making Quick Look Windows (QLW) appear

For any problem that prevents the window from starting, IRIS prints:

```
OUTPUT, Error in open_display call.
```

The **Radar Status** menu also indicates **Error** and **Exit** next to the window process.

If you cannot identify the problem from the error message:

- ▶ 1. Check that the workstation is turned on and the network is up and running.
2. Login as **radarop**.
3. Open the **Radar Status** menu and toggle the **Product Output** process off/on.
4. In the command prompt of the workstation where the window should appear, check the user rights by typing:

```
xhost+
```

5. Restart IRIS on your workstation by typing:

```
sudo systemctl restart iris
```



NOTICE! This command restarts all IRIS processes.

IRIS tests each process and restarts any that have stopped.

6. If the IRIS Quick Look Window (QLW) does not appear after typing **siris** in a terminal window:
 - a. Log in as **root**.
 - b. In the first line of the */etc/hosts* file, add the host name to the first line of the file:

```
127.0.0.1 <host-name> local host...
```

12.4 Replacing failed OS RAID disks

RAID1 is automatically configured on the server. However, in some cases, you may need to remove, recover, and add new devices to RAID.

In most cases, this requires removing the failing disk and installing a new one.



While you can do this while powered up, if the system allows you to power down, do so.

1. To check the status of the RAID1 disk, type:

```
cat /proc/mdstat
```

When RAID1 is working correctly, the terminal prints, for example:

```
Personalities : [raid1]

md126 : active raid1 sda[1] sdb[0]

      125032448 blocks super external:/md127/0 [2/2] [UU]

md127 : inactive sdb[1](S) sda[0](S)

      4520 blocks super external:imsm
```

- [UU] indicates that both disks are operational.
- If there is a problem with one of the disks, the [UU] string is [_U] or [U_].

2. Check if disk **sda** or **sdb** has failed.
3. To remove the disk from RAID configuration, type:



Take care when removing the failing disk. Remove only the disk identified as failing. In the following example, it is **sdb**.

```
mdadm --manage /dev/md/imsm0 --remove /dev/sdb
```

The terminal prints:

```
mdadm: hot removed /dev/sdb from /dev/md/imsm0
```

4. Power down computer, replace the failing disk, and reboot
5. To create the partition on the replacement disk, type:

```
sfdisk -d /dev/sda | sfdisk /dev/sdb
```

6. To verify the partition, type:

```
fdisk -l
```

7. To add a new disk to the raid array, type:

```
mdadm --manage /dev/md/ims0 --add /dev/sdb
```

8. To check the recovery process, type:

```
cat /proc/mdstat
```

The terminal prints:

```
[root@wes-install ~]# cat /proc/mdstat  
  
Personalities : [raid1]  
  
md126 : active raid1 sdb[2] sda[1]  
  
      125032448 blocks super external:/md127/0 [2/2] [UU]  
  
md127 : inactive sdb[1](S) sda[0](S)  
  
      4520 blocks super external:ims0  
  
unused devices: <none>
```

Appendix A. Installing AlmaLinux

A.1 Overview to installing AlmaLinux



IRIS RDA 10.2.0 requires the AlmaLinux 9 operating system.

Vaisala provides a customized ISO image for AlmaLinux on the Vaisala FTP website at:

<https://ftp.sigmet.vaisala.com/files/releases/AlmaLinux/>

Vaisala supports two installation methods from the Vaisala spin version of the ISO image:

- Automatic - unattended installation
- Manual - interactive installation

For both installation methods you can use the local USB device as your installation media.

We recommend that you use the automatic process unless you have special system configuration needs or if your custom configuration fails the automatic installation process.

Installing Linux requires a Linux software installation tree and a boot device. You must transfer the AlmaLinux distributions ISO images to the media that you are going to use in the installation.

You need the following to create installation media:

- PC running Windows 10/11, or AlmaLinux
 - USB port and USB Flash Drive 64 GB
- Vaisala recommends a USB 3.0 drive because data transfer is much faster than USB 2.0.

A.2 Creating installation media

After creating and initializing the installation media, you can run the installation process.


A.2.1 Creating USB installation media on Windows

These instructions apply to Windows 10 and Windows 11.


When creating USB installation media on Windows, use a standalone program such as `rufus` (available at <http://rufus.akeo.ie/>). Follow the on-screen instructions.

- ▶ 1. Launch `rufus` by double-clicking the program icon.
2. Insert a USB drive in the USB port.

3. Select the drop-down list to the right of the **Create a bootable disk using**, and select **ISO Image**.



4. Select the **Disc** icon and then select the iso image.
5. Select **Write in DD Image mode** if a warning for the hybrid ISO image is displayed.



6. Select **Close**.

A.2.2 Creating USB installation media on Linux (AlmaLinux)



NOTICE! This operation destroys data on the device you operate on.

- ▶ 1. Run **\$ lsblk** to list block devices on your system. Take note of the output.
2. Insert a USB drive in the USB port.
3. Run **\$ lsblk**.
Compare the output to the previous step. The additional block device from this output is your USB drive.
4. Run **\$ dd if=path/toAlmalinux.iso of=/dev/xxx**
Where */dev/xxx* is the path to the USB drive. Do not use the partition number for the USB drive.
For example: */dev/sdc*.


A.3 Installing AlmaLinux automatically

The automated installation uses KICKSTART to run an unattended installation.


The instructions in this section are for the Vaisala-provided server. If you are using a different system, consult your systems manual for instructions.

- ▶ 1. Power up the system by pressing the power button on the server.
2. Insert the USB drive into the USB port. If you are using the USB port for the first time, this also enables the port.

3. In the AlmaLinux 9.2 window, select **Install AlmaLinux 9.2**, and press **Enter**.



4. The installation starts. When prompted, configure the hostname and IP address.
 - For one port, configure the internal network: Select **Configure as static (default is DHCP)?**: Y, and enter the IP address **10.0.2.1**.
 - Configure a second port as DHCP by selecting **Configure as static (default is DHCP)?**: N.



Then the installation will continue.

- a. In the **Installation Summary** window, select **Installation Destination**.
 - b. Create new partitions: **/**, **/boot**, **swap**, **/srv**, and **boot/efi**.
See chapters [Partitioning the destination disk \(page 69\)](#) and [Recommended partitioning settings \(page 69\)](#).
 - c. In the **Installation Summary** window, select **Begin Installation**.
5. When the installation is complete, the system will reboot automatically.
 6. Vaisala strongly recommends changing any default passwords.
 7. Select **Application > System Tools > Settings GUI**.

8. In **Region & Language**, configure your language settings.

9. Depending on your configuration, you may need to configure the ports.
- If you are using **Dell PowerEdge R440** server, use ports **em1** and **em2**.
 - If you have an **American Megatrend** server, your **enp9s0** port is automatically set to communicate with the IFDR10 on a 10.0.1.x network.




NOTICE! Do not reconfigure the network port to IFDR10.


- If you have a **SuperMicro** server, your network settings for IFDR10 are not pre-initialized. The IFDR10 10.0.1.x network is usually configured on the **enp9s0**, **enp1s0f1**, or **eth1** ports but is not limited to these ports.

This example uses the `enp1s0f1` port.


- a. Select **System Tools > Settings > Network**.



- b. In the **Network** window, select the gear icon in the lower right corner.
- c. Select the **Identity** tab.
In **MTU**, type **8192**.



- d. Select the **Details** tab.
Select **Connect automatically** and **Make available to other users**.



- e. In the right pane, select **IPv4**.

The screenshot shows the NetworkManager configuration window for a wired connection. The 'IPv4' tab is selected. Under 'IPv4 Method', the 'Manual' radio button is chosen. The 'Addresses' section contains a table with the following data:

Address	Netmask	Gateway
10.0.1.20	255.255.255.0	

The 'DNS' section is set to 'Automatic' and 'ON'. Below it is a text input field for DNS servers. The 'Routes' section is also set to 'Automatic' and 'ON', with a table for route configuration:

Address	Netmask	Gateway	Metric

Change **Addressing** to **Manual**.

In the **Address**, **Netmask**, and **Gateway** fields, type enter the test shown in the figure.

Select **Apply**.

More information

- [Recommended partitioning settings \(page 69\)](#)


A.4 Installing AlmaLinux manually (interactive)

A.4.1 Booting the system for manual installation

You must configure the system to boot from the media device that you have created.

The instructions in this section are for the Vaisala-provided server. If you are using a different system, consult your systems manual for instructions.

- ▶ 1. Power up the system by pressing the power button on the server.
2. Insert the USB drive into the USB port. If you are using the USB port for the first time, this also enables the port.
3. In the AlmaLinux 9.2 window, select **Install AlmaLinux 8.7**, and press **Enter**.




4. Select a language.
(This instruction assumes that **English (United States)** is selected.)
5. Select **Continue**.
6. Select the keyboard icon to select the keyboard type (default is **English**).
7. Select **Language Support** to select the language.
8. Select **Time & Date** to set up the time and date.
 - Region: **Etc**
 - City: **Coordinated Universal Time**
9. Select **USER CREATION**.
The **User creation** window opens.
 - a. In the user name text box, enter user account name or if you wish to have the user account name generated from the full name, enter the user's full name in the **Full name** text box.
 - b. In the password text box, enter the user account's password.
 - c. In the confirm text box, re-enter the user account's password.
 - d. Select **Done**.
If your password is weak, you are prompted to select **Done** a second time.
10. For **Installation Source**, select the default value (**Local media**).
11. Select **Software Selection (Server with GUI)**, and for additional software, select **Development Tools**.
12. Click on **Installation Destination**

13. Select local Standard Disks, and check the **Custom** button.
14. Select **Done**.
15. Select **LVM** for the partition scheme from the drop-down menu.
Select the **+** icon to add a partition. For more information about the partitioning, see [Partitioning the destination disk \(page 69\)](#).

A.4.2 Configuring the system and network

- ▶ 1. In the **Installation summary** window, select **Network & Host Name**.
2. Enter the host name in the **Host name** text box in the lower left corner.
 - a. Select the network device you wish to configure listed in the panel on the left hand side. The selected device is highlighted.
 - b. In some interfaces, to enable the network interface, select the blank button next to **OFF** in the upper right-hand corner.
If the button exists, slide the button to the **ON** position.
 - c. Select **Configure** at the bottom right-hand corner to display the **Editing** window.
3. Select the **General** tab to set the connectivity options.



- a. Select **Automatically connect to this network when it is available**.
- b. Select **All users may connect to this network**.

4. Select the **IPv4 Settings** tab.

Editing enp0s3

Connection name:

General Ethernet 802.1X Security DCB **IPv4 Settings** IPv6 Settings

Method:

Addresses

Address	Netmask	Gateway
10.0.1.20	24	0.0.0.0

DNS servers:

Search domains:

DHCP client ID:


Require IPv4 addressing for this connection to complete

- a. In the **Method** drop-down menu, select **Manual**.
 - b. Select **Add**.
 - c. Enter the IP address, netmask, and gateway in the text entry boxes under the headers.
 - d. If configuring your **eth0** interface, type your DNS server address in the **DNS server** field.
If configuring your **eth1** interface, leave this blank.
 - e. If configuring your **eth0** interface, type your domain name in the **Search** domains field.
If configuring your **eth1** interface, leave this blank.
 - f. Check the **Require IPv4 addressing for this connection** box near the bottom of the page.
5. Optional: If you are configuring the computer to run RDA software and connect to IFDR10, you need to configure Ethernet ports. See [Configuring the system and network for RDA and IFDR10 \(page 66\)](#).
 6. Select **Save** in the lower right corner to finish network configuration.
 7. Select **Done** in the upper left corner of the **Network and Host Name** tab to return to the **Installation summary** window.

A.4.2.1 Configuring the system and network for RDA and IFDR10


If you plan to run RDA software on this computer and connect to IFDR10, two Ethernet ports are required.

1. In the installation summary page, select **Network and Host Name**.
The required Ethernet ports should appear in the panel on the left hand side of the **Network and Host Name** window.
2. Select the **Ethernet** tab. In the **MTU** field, type **8192**.



The screenshot shows a window titled "Editing enp0s3" with a "Connection name" field containing "enp0s3". Below this is a tabbed interface with tabs for "General", "Ethernet", "802.1X Security", "DCB", "IPv4 Settings", and "IPv6 Settings". The "Ethernet" tab is active. The "Device" field is empty. The "Cloned MAC address" field is empty. The "MTU" field is set to "8192" with a "bytes" label and minus/plus buttons. The "Wake on LAN" section has several radio button options: "Default" (checked), "Phy", "Unicast", "Multicast", "Ignore", "Broadcast", "Arp", and "Magic". The "Wake on LAN password" field is empty. At the bottom right are "Cancel" and "Save" buttons.

3. Select the **IPv4 Settings** tab.



- a. In the **Method** drop-down menu, select **Manual**.
- b. Select **Add**.
- c. Enter the IP address, netmask, and gateway in the text entry boxes under the headers.
 - If you are configuring the Ethernet port connected to the Internet or your corporate network: The settings in this window are specific to your network configuration. If you are unsure what to enter in these fields, contact your IT support.
 - If you are configuring the Ethernet interface for direct connection to the IFDR10, use the following settings:

Setting	Value
Address	10.0.3.1
Netmask	24
Gateway	0.0.0.0

- d. Type your DNS server address in the **DNS server** field.
- e. Type your domain name in the **Search** domains field.
- f. Check the **Require IPv4 addressing for this connection** box near the bottom of the page.

4. Select **Save** in the lower right corner to finish network configuration.

5. Select **Done** in the upper left corner of the **Network and Host Name** window to return to the installation summary page.

A.4.3 Partitioning the destination disk

A.4.3.1 Recommended partitioning settings

Vaisala recommends the following disk partitioning.

You need the `/boot/efi` partition if your computer uses the UEFI boot.

Table 3 Recommended disk partitioning

Partition	File system type	Size
<code>/home</code>	XFS	50 GB
<code>/boot</code>	EXT4	500 MB
<code>/boot/efi</code>	EFI	600 MB
<code>/var</code>	XFS	100 GB
<code>/</code>	XFS	50 GB
<code>swap</code>	SWAP	size of RAM + 2 GB
<code>/srv</code>	XFS	All of the remaining disk space


Use the xfs file system for partitioning.

Partition `/srv` is a data partition.


If there is only a little disk space, you can decrease the size of the `/home` and `/` partitions by 10-20 GB.

A.4.3.2 Partitioning the destination disk automatically

- ▶ 1. In **INSTALLATION DESTINATION**, start manual partitioning:
 - a. Select the hard disk.
 - b. Select **Select Storage Configuration, Custom**.
 - c. Select **Done**.



2. Select **Click here to create them automatically.**



After creating the automatic partitions, you need to modify the partition manually in the next steps.


3. Modify the **/home** partition.

- a. Select the **/home** partition.
- b. Under **Desired Capacity**, set the size of the home partition (**/home**) to **50 GiB**.
- c. Set the **File System** to **ext4**.
- d. Select **Update Settings**.

4. Create the */var* partition:

- a. Select the plus (+) icon.

The **ADD A NEW MOUNT POINT** dialog appears.



ADD A NEW MOUNT POINT

More customization options are available after creating the mount point below.

Mount Point:

Desired Capacity:

- b. In **Mount Point**, type */var*

- c. Under **Desired Capacity**, set the size of the */var* partition by typing **50 GiB**.

- d. Select **Add mount point**.

5. Select **/boot**.

- a. Under **Desired Capacity**, set the size of the */boot* partition by typing **500 MiB**.

- b. Select **Update Settings**.

6. Select **/**.

- a. Under **Desired Capacity**, set the size of the root partition (*/*) by typing **50 GiB**.

- b. Select **Update Settings**.

7. Select **swap**.


- a. Under **Desired Capacity**, set the size of the swap to the size that corresponds to RAM + 2 GB.

- b. Select **Update Settings**.

8. Create the `/srv` partition:

a. Select the plus (+) icon.

The **ADD A NEW MOUNT POINT** dialog appears.



b. In **Mount Point**, type `/srv`

c. Under **Desired Capacity**, use nearly all the available server space (indicated in the pink box) for the `/srv` partition by typing, for example, **284 GiB**.




Figure 2 Example of available disk space

d. Select **Add mount point**.

9. Select **Done**.

10. In the window listing the partitions, check that the partitions are defined as described in [Recommended partitioning settings \(page 69\)](#).

11. Select **Done > Accept Changes**.


A.4.3.3 Partitioning the destination disk manually

- ▶ 1. On the installation summary page, select **Destination Installation**.
- 2. To select the destination disk for the AlmaLinux installation, select the **Disk** icon. Once selected, a check mark appears on the icon.
- 3. Select **Storage configuration > Custom**. For recommended settings, see [Recommended partitioning settings \(page 69\)](#).
- 4. Follow the instructions to create new partitions, or, if needed, to re-use or delete existing partitions.

A.4.3.3.1 Deleting existing partitions

If you do not want to use the existing partitions, you must delete them to provide disk space for your installation.

- ▶ 1. Select the arrow to the left of the drive name you want to modify to expand the partitioning scheme.
- 2. Select a partition to delete.
- 3. Select a minus sign (-) icon to delete the partition.
- 4. On the pop-up window, check **Delete all other filesystems....** and select **Delete it**.



A.4.3.3.2 Creating new partitions



Vaisala recommends the LVM partitioning scheme.

- ▶ 1. If the `/home` partition exists, delete it by selecting the minus (-) icon.
- 2. Select the plus (+) icon to add partitions.
Do this 4 times, once for each partition.

3. For each new directory, do the following:

- a. From the **Mount Point** menu, select the directory.
 - b. Go to **ADD A NEW MOUNT POINT > Desired Capacity**, and type the value recommended in [Recommended partitioning settings \(page 69\)](#).
 - c. Select **Add mount point**.
4. Create the `/srv` partition:
 - a. In the **Mount Point** field, type `/srv`.
Type a number larger than the remaining data size. For example: **9999999999**.
 - b. Select **Add mount point**.
 5. One at a time, select each partition, and modify the value in the **Desired Capacity** field with recommended values.
For **File System Type**, you can select either **EXT4** or **xfs**.
 6. Select **Done > Accept changes** to finish partitioning.

When you have completed partitioning, do one of the following:

- If you are doing a manual installation, go to [Starting the installation \(page 76\)](#).
- If you are doing an automatic installation, go back to [Installing AlmaLinux automatically \(page 57\)](#).

A.4.3.3.3 Re-using existing partitions

If your disk has an operating system installed, the partitioning scheme list is displayed.

- ▶ 1. To expand the partitioning scheme, select the arrow to the left of the drive name you want to re-use.
2. In the partition window, for each partition shown in the left pane, select the partition, and enter the name shown in the **Mount Point** field.
For the **swap** partition, you do not need to enter the mount point name, but you still need to perform steps 3 and 4.
3. Check the **Reformat** check box next to the **File System** drop-down list.
4. Select **Update Settings**.

5. When you have updated the settings for all the partitions, select **Done**.
6. Select **Accept Changes** to return to the installation summary page.

A.4.4 Starting the installation

Before starting the installation, make sure you have your root password and user account information.

- ▶ 1. In the lower right corner of the installation summary page, select **Begin installation**.
The user settings configuration page appears.
- 2. While the installation process is in progress and before the end of the installation, configure the **root** password.
- 3. When installation status shows complete, select **Reboot** and remove the installation media.
The installation takes 20 ... 30 minutes.
- 4. If the server does not reboot automatically, use the power button to power cycle the system.
- 5. If on the first boot you see the prompt window **Accept the License Information**, in the initial setup window:
 - a. Select **License Information**.
 - b. Check the **I accept the license agreement** box.
 - c. Select **Done**.
 - d. Select **Finish configuration**.
Login screen is displayed.
- 6. Disable monitor negotiation.
- 7. The first time you login to each new account, follow the series of windows to verify your keyboard and localization settings.
 - a. Select **Next** until you get to the thank you screen.
 - b. Select **Start using**.
- 8. Log out of the user account to continue with the installation.

More information

- ▶ [Disabling monitor negotiation \(page 76\)](#)

A.4.5 Disabling monitor negotiation

During manual operating system installations, Vaisala recommends disabling monitor negotiation to ensure that the server recognizes the monitors.

1. In the `/etc/default/grub` file, after the `quiet` in `GRUB_CMDLINE_LINUX` add:

```
nomodeset
```

2. Save your changes.
3. To update the configuration file, run the following script:

```
cd /boot/grub2/  
grub2-mkconfig -o grub.cfg
```

A.4.6 Configuring time sync with chronyd

You can configure your machine to time sync with another machine using `chronyd`.

1. In the `/etc/crony.conf` file, update the lines that start with the word `server` by removing the default server lines and adding your own. For example:

```
# configure the servers for synchronization using ip address or name  
server 198.102.75.10 iburst  
server 0.centos.pool.ntp.org iburst
```

2. If `chronyd` is already running and you would like changes to take effect, use the following command:

```
#systemctl restart chronyd.service
```

3. If you would like NTP to start automatically on restart, type:

```
#systemctl enable chronyd.service
```

This takes effect after the next reboot. To start without rebooting, type:

```
#systemctl start chronyd.service
```

The system takes 15 minutes to sync the time. If the times are more than 10 minutes apart, NTP assumes there is an error and does not change the time.

4. To check on the status of **chronyd**, type:

```
# chronyd sources -v
```

The first character before the server host is ***** when it is time synced.

A.4.7 Rebooting the system

- ▶ 1. When the installation is complete, select **Reboot** to reboot the system.
2. Depending on your system bios boot sequence setting, you may need to remove the installation media right after you see the system shutdown complete window flash by in order to boot using the hard drive.

A.4.8 Logging in with your user account

After rebooting, the login window shows the user account you created.

- ▶ 1. Select your user account, and enter your password in the text box.
2. Select **Sign in**.
The first time you log in to each new user account, you are asked to set some initialization settings. The default settings are normally properly set during the installation process, and no setting changes should be required.
3. In the **Welcome** window, select your language, and select **Next**.
4. In the **Input Sources** window, verify your source, and select **Next**.
5. In the **On-line Accounts** window, select **Next**.
6. In the **Thank you** window, select **Start using AlmaLinux**.
7. Read the **GNOME Help** window and press **X** in the upper right corner to close the window.

The installation and initialization process for AlmaLinux is complete.

Appendix B. IRIS Diagnostic Utilities

B.1 ps_iris command

Use the **ps_iris** command to list currently active IRIS, antenna, and utility processes, including information about their owner UID, PID, time start time, and total CPU time.



To stop a process, use the **PID** as an argument to the **kill** command.

For example:

Detached Processes:

USER	GROUP	PID	PPID	NI	PRI	%CPU	TIME	%MEM	VSZ	COMMAND
operator	users	3353	1	0	19	0.0	0:02	0.0	168216	server IRIS_SERVER
operator	users	3355	1	4	15	0.0	0:00	0.0	142236	sserver IRIS_SSERVER
operator	users	3399	1	-8	27	0.0	0:49	0.0	136788	ingfio IRIS_INGFIO
operator	users	3407	1	4	15	0.0	0:00	0.0	136768	network IRIS_NETWORK
operator	users	3411	1	8	11	0.4	7:17	0.0	143124	product IRIS_PRODUCT
operator	users	3413	1	8	11	0.0	0:00	0.0	157800	reingest
IRIS_REINGEST										
operator	users	3415	1	4	15	0.0	0:00	0.1	180620	output IRIS_OUTPUT001
operator	users	3418	1	4	15	0.0	0:01	0.0	156556	output IRIS_OUTPUT002
operator	users	3420	1	0	19	0.0	0:02	0.0	136776	input IRIS_INPUT01
operator	users	3423	1	0	19	0.0	0:09	0.0	138996	watchdog
IRIS_WATCHDOG										
operator	users	23970	1	-8	27	0.0	0:08	0.0	142164	ingest IRIS_INGEST

Antenna Processes:

USER	GROUP	PID	PPID	NI	PRI	%CPU	TIME	%MEM	VSZ	COMMAND
operator	users	1756	1	0	19	0.0	0:04	0.0	115676	ant_logd ANT_LOGD
operator	users	1789	1	-15	34	0.0	0:51	0.0	115684	ant_rcvd ANT_RCVD
operator	users	1793	1789	-15	34	0.0	1:10	0.0	115684	ant_rcvd ANT_RCVD
operator	users	1823	1	-15	34	0.0	1:08	0.0	115680	ant_xmtd ANT_XMTD

```

Stand-alone Utilities:
  USER      GROUP      PID  PPID  NI  PRI  %CPU   TIME  %MEM   VSZ  COMMAND
  radarop   radarop   23933 23923  0  19  0.0    0:00  0.0  116244 audio
iris_audio
  operator  users     4321  4319  4  15  0.0    0:00  0.0   12636 clntRecv
CLNT_RECV_WINDOW -pipe 8
  radarop   radarop   23923  4163  0  19  0.0    0:04  0.0  189464 iris
  radarop   radarop   23934 23923  0  19  0.0    0:00  0.0  116236 iris_clnt_rcv
7 1073741826
  operator  users     3330    1  0  19  4.6   67:30  0.0  699324 /rcp8 -
console /dev/null
  operator  users     2021    1  0  19  9.4  138:57  0.4  796880 /rvp10 -
daemon
  operator  users     2297  2021  -  50 12.0  176:43  0.3  275560 rvp10proc
RVP10_PROC-0
  operator  users     2347  2021  -  50 11.8  172:44  0.3  275556 rvp10proc
RVP10_PROC-1

```

B.2 show_iris command

Use the **show_iris** command to show information about the IRIS process: When it started, the present state of semaphores and event flags, and the current inventory of in-use products.

The **show_iris** command also provides command line options for in-use bits. For more information, type **show_iris -help**.

```

$ show_iris
IRIS Activity on 'hot' at: 09:52:52 17 SEP 1999
IRIS V7.11 was started at 16:19:38 16 SEP 1999 by 'joe'.
Manual startup from TTY:'/dev/tty' ; Restarts:1
Features License: 00004001-000101-WAHRMA-01-Y9ANHF
Products License: 000007FF-000101-WAHRMA-03-WFW4KR

```

Present states of Semaphores...

```
PROCESS CONTROL: FREE (ID: 5833)    PROCESS MODES: FREE (ID: 5826)
TASK SCHEDULE: FREE (ID: 5834)    PRODUCT SCHEDULE: FREE (ID: 5831)
INGEST DIRECTORY: FREE (ID: 5831)  PRODUCT DIRECTORY: FREE (ID: 5849)
DEVICE TABLE: FREE (ID: 5852)    MODE SWITCH TABLE: FREE (ID: 5834)
ARCHIVE DIRECTORY: FREE (ID: 5834)  ERROR LOG: FREE (ID: 5834)
```

Present states of Event Flags...

```
RTDISP: CLEAR    INGEST: CLEAR
INGFIO: CLEAR    INGFIO MAPPING: SET
INGFIO WAITING: SET    WATCHDOG: CLEAR
PRODUCT: CLEAR    REINGEST: CLEAR
NETWORK: CLEAR    NORDRAD: CLEAR
GLOBAL MAPPED: SET
```

```
Event Flags SET for Output Processes: 7 8
```

```
Event Flags SET for Network Child Processes: 1 2 3 4 5 6 7 8 9 10 11 12 13 14
15 16
```

```
Checking INGEST inventory for in-use files:
```

```
Total files checked: 92, total in use: 0.
```

```
Checking PRODUCT inventory for in-use files:
```

```
Total files checked: 260, total in use: 0.
```

```

===== Product Inventory Contents =====
Prod Type          Count          Size(Mb)          Kept Count        Kept Size
PPI                 0              0.00             0                 0.00
RHI                 0              0.00             0                 0.00
CAPPI              159            92.06            21                60.92
Cross Section      0              0.00             0                 0.00
Echo Tops          0              0.00             0                 0.00
Tracking           0              0.00             0                 0.00
Hourly Rainfall    0              0.00             0                 0.00
N Hours Rainfall   0              0.00             0                 0.00
Vol. Vel. Proc.    0              0.00             0                 0.00
Vert.Int. Liquid   0              0.00             0                 0.00
Wind Shear         0              0.00             0                 0.00
Warning            1              0.01             0                 0.01
Real Time PPI      0              0.00             0                 0.00
Real Time RHI      0              0.00             0                 0.00
Raw Data           73            52.35            73                52.35
Max with panels    0              0.00             0                 0.00
User Map           0              0.00             0                 0.00
User Section       0              0.00             0                 0.00
User Other         0              0.00             0                 0.00
Status             25            0.06             0                 0.00
Shear Line         0              0.00             0                 0.00
Horizontal Wind    0              0.00             0                 0.00
Beam Pattern       0              0.00             0                 0.00
Text               0              0.00             0                 0.00
Forecast           0              0.00             0                 0.00
Multi-Doppler     2              15.36            2                 15.36
Image              0              0.00             0                 0.00
Composite          0              0.00             0                 0.00
LLWAS              0              0.00             0                 0.00
                   260            159.84 Mb        97                128.65 Mb

```

B.3 sigmet_env Command

Use **sigmet_env** to test or troubleshoot items associated with an IRIS installation.

To sue the command, log in as a normal IRIS user, run **sigmet_env**. The **sigmet_env** command checks the following:

- That all the IRIS operators and observers are in the */etc/users* file.
- That all IRIS environment variables that point to directories are defined and the directory exists, and the directory can be read and written as required.
- For obvious bad file names in the saved menu directory.
- That IRIS executable files which require the **set-UID-on-execute** bit set are set with the correct UID.
- The RDA (RVP/RCP) environment.

The following example shows a case with a bad file name of *.TSC*.

```
$ sigmet_env
Checking IRIS_OPERATORS list...
Checking IRIS_OBSERVERS list...
Checking installation directories...
Checking configuration directories...
Checking data directories...
Checking file names in IRIS_MENU...
Bad menu filename: '/etc/vaisala/irisrda/menu/.TSC'
Checking root file ownerships...

Errors Detected -- Please Check Printout
```

Appendix C. Alternative Configurations

C.1 Defining the operator list in the startup file

Most environments can function with **radarop** and **observer** users without any further definitions. If you wish to manage named users, follow the instructions below.

The `/etc/vaisala/irisrda/profile.conf` file defines some of the base configuration, including the lists of users who can operate IRIS fully, and who can observe its operation but not make any changes.



Every IRIS user must share group access to files owned by the operator by being a member of the users group.

1. Edit the file and change these as needed.

```
operators='radarop operator john george mary root'  
observers='observer'
```

2. Check your environment by typing:

```
$ env | grep IRIS
```

Warranty

For standard warranty terms and conditions, see vaisala.com/warranty.

Please observe that any such warranty may not be valid in case of damage due to normal wear and tear, exceptional operating conditions, negligent handling or installation, or unauthorized modifications. Please see the applicable supply contract or Conditions of Sale for details of the warranty for each product.

Technical support



Contact Vaisala technical support at helpdesk@vaisala.com. Provide at least the following supporting information as applicable:

- Product name, model, and serial number
- Software/Firmware version
- Name and location of the installation site
- Name and contact information of a technical person who can provide further information on the problem

For more information, see vaisala.com/support.

Recycling



Recycle all applicable material according to local regulations.

VAISALA

