

Table of Contents

Preface	vii
1. Introduction to IRIS Utilities	1-1
1.1 Radar/Antenna	1-4
1.1.1 Configuring the Antenna	1-4
1.1.2 Monitoring the Antenna	1-5
1.1.3 Testing the Antenna	1-5
1.2 Signal Processor	1-6
1.2.1 Configuring the Signal Processor	1-6
1.2.2 Calibrating the RVP7 or RVP8 Signal Processor	1-7
1.2.3 Monitoring the Signal Processor	1-7
1.2.4 Testing the Signal Processor	1-7
1.3 Running the IRIS Utilities	1-8
1.3.1 Running the Utilities Locally from a Terminal Window	1-8
1.3.2 Running the Utilities Locally Using the utils menu	1-9
1.3.3 Running Utilities or the utils Menu from a Remote Workstation	1-10
1.4 Getting Online Help	1-12
1.4.1 Moving Around in the Document	1-12
1.4.2 Searching for Information	1-12
1.4.3 Printing Online Documentation	1-13
1.4.4 Accessing Other SIGMET Online Books	1-13
2. Antenna Utility	2-1
2.1 Invoking Antenna	2-2
2.2 Antenna Menu	2-3
2.2.1 Azimuth and Elevation Section	2-4
2.2.2 Control Panel	2-6
2.2.3 Status Panel	2-8
2.3 Antenna Commands	2-10
2.3.1 I/O Summary Menu	2-10
2.4 Testing Antenna Safeguards	2-13
2.5 Running Antenna in Sun Tracking Mode	2-14
2.6 Stable Platform Display	2-16
2.6.1 Overview of Stable Platform Concepts	2-16
2.6.2 Invoking the Stable Platform Display Section	2-17
2.6.3 AZ/EL Graphical Display Features	2-17
2.6.4 Stable Platform Parameters Display	2-18
2.6.5 Sun Tracking Check of Stable Platform Corrections	2-19

3. Ascope Utility	3-1
3.1 Invoking Ascope	3-2
3.2 Ascope Menu	3-3
3.2.1 Antenna Status	3-4
3.2.2 Display Status	3-4
3.2.3 Radar Status	3-6
3.2.4 Processing Status	3-8
3.2.5 Filters	3-11
3.2.6 Calibration	3-13
3.3 Ascope Plots	3-16
3.3.1 Reflectivity vs. Range Plot (T and Z)	3-16
3.3.2 Doppler Mean Velocity vs. Range Plot (V)	3-17
3.3.3 Spectrum Width vs. Range Plot (W)	3-17
3.3.4 ZDR vs. Range Plot (ZDR) (available with ZDR option)	3-18
3.3.5 Linear Channel A/D vs. Range Plot (I and Q or Mag and Arg)	3-18
3.3.6 LOG Channel A/D vs. Range Plots (ALOG)	3-18
3.3.7 Doppler Spectrum Plot (Spec)	3-19
3.3.8 Time Series at a Selected Range (I, Q, and LOG)	3-20
3.4 Ascope Commands	3-22
3.5 Data Recording and Playback	3-23
3.5.1 The “Record” Menu	3-23
3.5.2 The “Playback” Menu	3-26
3.5.3 Format of the Recorded Data	3-28
3.6 The Digital Signal Simulator	3-30
3.6.1 Testing with the Digital Signal Simulator	3-33
3.7 Ascope Checkup Procedures	3-35
3.7.1 Coarse Adjustment of the Gain and Offset Pots	3-35
3.7.2 Fine Adjustment of the Gain and Offset Pots	3-37
3.7.3 Phase and Amplitude Stability Checks	3-37
3.7.4 Doppler Velocity Sign Check	3-39
4. Bitex Utility	4-1
4.1 Invoking Bitex	4-2
4.2 Bitex Window	4-3
4.3 Histograms	4-6
4.4 Bitex Commands	4-7
4.5 Customizing of Bitex	4-8
4.5.1 General – Bitex Customization Options	4-8
4.5.2 Bitex Customization Tools	4-9
4.5.3 Bitex Panel Options	4-10
4.5.4 Bitex Data Point Configuration	4-11

5. Color Setup Utility	5-1
5.1 Overview	5-1
5.2 Starting color_setup	5-3
5.3 Configuring a Color Scale	5-3
5.4 Configuring a Color Set	5-8
5.5 Configuring the Color Palette	5-10
5.6 Configuring the Special Colors	5-10
5.7 Example Values to Get Started	5-11
6. Dspx Utility	6-1
6.1 Invoking Dspx	6-1
6.2 Dspx Commands and Prompts	6-1
6.3 Sample Dspx Session	6-2
7. Overlay Utility	7-1
7.1 Invoking Overlay	7-2
7.2 Listing and Printing Overlay Files	7-7
7.3 Viewing an Overlay with overlay	7-8
7.4 Format of Overlay Files	7-10
7.4.1 Overlay Header	7-10
7.4.2 Text Strings and Bitmap Icons	7-11
7.4.3 Map Outlines	7-12
7.4.4 Layer Functions and Command	7-12
7.4.5 Solid Underlay Regions	7-13
7.4.6 GIF Underlay Regions	7-13
7.4.7 Example of an Overlay File	7-16
7.5 Format of catchment files	7-19
7.6 Creating and Editing Overlay Files	7-20
8. Real Time Display	8-1
8.1 Real Time Display Menu Features	8-2
8.2 Configuring the Real Time Display Transmitter	8-8
9. Setup Utility	9-1
9.1 Invoking Setup and Built-In Error Checking	9-2
9.2 Radar Video Processor	9-4
9.2.1 System Type	9-4
9.2.2 Optional Data Parameters	9-5
9.2.3 System Parameters	9-8
9.2.4 Calibration	9-10
9.2.5 Signal Processing Options	9-12
9.2.6 Data Simulations	9-14
9.2.7 Pulsewidth Definitions	9-15

9.2.8	Digital IF Gain Control (RVP6 REV.B)	9-17
9.2.9	Real Time Display (RTD)	9-19
9.3	Radar Control Processor	9-21
9.3.1	Interface to RCP	9-21
9.3.2	Advanced Interface Features	9-24
9.3.3	Packet and Data Logging	9-25
9.3.4	Radar Site and Antenna Placement	9-26
9.3.5	Antenna Characteristics	9-27
9.3.6	Control and Support Features	9-28
9.3.7	Control Bit Definitions	9-30
9.3.8	Status Bit Definitions	9-32
9.3.9	Network Status Reports	9-34
9.3.10	RST Mode Requests	9-35
9.4	IRIS Input Setups	9-37
9.5	IRIS General Setups	9-40
9.5.1	Modes and Protocols	9-40
9.5.2	Speech and Signaling	9-41
9.5.3	File System Quotas	9-43
9.5.4	Run-Time Priorities	9-45
9.5.5	Window Alert Configuration	9-46
9.5.6	Site Names and Site Codes	9-47
9.6	License Setups	9-48
9.7	IRIS Ingest Setups	9-50
9.7.1	Data Source Selection	9-50
9.7.2	Signal Processing and Data Storage	9-51
9.7.3	Scanning Options	9-52
9.7.4	DSP Noise Sampling	9-55
9.7.5	Transmitter Control	9-57
9.7.6	Clutter Suppression	9-58
9.7.7	Intervening Attenuation	9-58
9.7.8	Unfolding of Velocity	9-59
9.7.9	Velocity Fallspeed Correction	9-60
9.8	IRIS Product Setups	9-61
9.8.1	Product Generation	9-61
9.8.2	Reflectivity Profile and Wind	9-63
9.8.3	Status Products	9-64
9.8.4	Product Transmission and Display	9-65
9.8.5	Product Scheduling Priority	9-66
9.8.6	Warning Regions	9-67
9.9	IRIS Output Devices Setups	9-68
9.9.1	Output Device General Specifications	9-68
9.9.2	Printer Specific Parameters	9-69

9.9.3	Window Specific Parameters	9-70
9.9.4	Network Specific Parameters	9-71
9.9.5	Archive Specific Parameters	9-75
9.9.6	Link Specific Parameters	9-77
9.9.7	Link Device Parameters	9-77
9.10	IRIS Web Setups	9-79
10.	Suncal Utility	10-1
10.1	Invoking Suncal and Options	10-2
10.2	Calibration Calculations	10-3
10.3	Suncal Configuration File	10-3
11.	RVP8/RCP8 Network Export Utilities	11-1
11.1	Starting and Stopping DspExport and AntExport	11-2
11.2	Example Network Configurations	11-5
11.2.1	Case 1: Separate PC's for RVP8, RCP8 and Host (e.g., IRIS)	11-6
11.2.2	Case 2: Separate RVP8, Combined RCP8/RCW (e.g., IRIS Host) ...	11-7
11.2.3	Case 3: Combined RVP8, RCP8/RCW (e.g., IRIS Host)	11-8
11.2.4	Case 4: Combined RVP8, IRIS Host	11-9
11.2.5	Case 5: AMR with separate Main RCP8 and Host	11-10
11.2.6	Case 6: Separate RVP8, RCP8, IRIS and a remote workstation	11-11
11.3	Non-Network Antenna Angles to RVP8	11-12
11.4	RCP8 on Serial Interface	11-13
12.	Zauto7 Utility	12-1
12.1	Invoking Zauto	12-2
12.1.1	Before running zauto	12-2
12.1.2	Invoking zauto	12-2
12.2	Zauto Menu	12-3
12.2.1	Calibration Parameters	12-4
12.2.2	Calibration Plot	12-5
12.2.3	Calibration Display	12-7
12.2.4	Configuration Menu	12-9
12.2.5	Results Display	12-10
12.3	Zauto Commands	12-13
12.4	Manually Calibrating the Signal Processor	12-14
12.5	Automatically Calibrating the Signal Processor	12-16
12.6	The Siggen Calibration File	12-18
13.	Zcal Utility	13-1
13.1	Invoking Zcal	13-1
13.2	Zcal Commands and Prompts	13-2
13.3	Changing LOG Receiver Calibration Numbers	13-3

Index	Index-1
--------------------	----------------

Figures

Figure 1–1: Typical Antenna Installation	1–4
Figure 1–2: Typical Signal Processor Installation	1–6
Figure 5–1: Steps in Defining a Color Scale	5–2
Figure 5–2: Color Configuration Menu Example for Velocity	5–4
Figure 5–3: Color Set Configuration Menu example for velocity.	5–9
Figure 7–1: Sample Overlay Display	7–9
Figure 9–1: Setup Utility Main Screen for IRIS and RDA	9–2

Tables

Table 1–1: IRIS Utilities by Function	1–1
Table 1–2: Summary of IRIS Utilities	1–2
Table 3–1: Coherency Relationships	3–38
Table 6–1: DspX Commands	6–1
Table 9–1: Input Pipes Supplied with IRIS	9–38
Table 9–2: Output Pipes Supplied with IRIS	9–72
Table 9–3: Copy Scripts Supplied with IRIS	9–74
Table 10–1: Suncal Command Line Options	10–2
Table 13–1: Zcal Commands	13–2